

Work with Members Using PDM

CSTST72A

File HARMONIZER
Library JOEB Position to

Type options, press Enter.

- 2=Edit 3=Copy 4=Delete 5=Display 6=Print 7=Rename
8=Display description 9=Save 13=Change text 14=Compile 15=Create module...

Table with 4 columns: Opt, Member, Type, Text. Rows include PGM1MERGE, PGM1V1, and PGM1V2.

Bottom

Parameters or command

===>
F3=Exit F4=Prompt F5=Refresh F6=Create
F9=Retrieve F10=Command entry F23=More options F24=More keys

Columns . . . : 1 80 Browse JOEB/HARMONIZER
SEU==> PGM1V1

FMT ** ...+... 1 ...+... 2 ...+... 3 ...+... 4 ...+... 5 ...+... 6 ...+... 7 ...+... 8
***** Beginning of data *****
0001.00 PGM 210819
0002.00 /* THIS IS PROGRAM 1 VERSION 1 */ 210819
0003.00 CALL PGM(PGM1) 210819
0004.00 CALL PGM(PGM2) 210819
0005.00 ENDPGM 210819
***** End of data *****

- F3=Exit F5=Refresh F9=Retrieve F10=Cursor F11=Toggle F12=Cancel
F16=Repeat find F24=More keys

Work with Members Using PDM

CSTST72A

File HARMONIZER
Library JOEB Position to

Type options, press Enter.

- 2=Edit 3=Copy 4=Delete 5=Display 6=Print 7=Rename
8=Display description 9=Save 13=Change text 14=Compile 15=Create module...

Table with 4 columns: Opt, Member, Type, Text. Rows include PGM1MERGE, PGM1V1, and PGM1V2.

Bottom

Parameters or command

==>

- F3=Exit F4=Prompt F5=Refresh F6=Create
F9=Retrieve F10=Command entry F23=More options F24=More keys

Columns : 1 80

Browse

JOEB/HARMONIZER

SEU==> PGM1V2

FMT ** ...+... 1 ...+... 2 ...+... 3 ...+... 4 ...+... 5 ...+... 6 ...+... 7 ...+... 8
***** Beginning of data *****
0001.00 PGM 210819
0002.00 /* THIS IS PROGRAM1 VERSION 2 */ 210819
0003.00 CALL PGM(PGM2) 210819
0004.00 CALL PGM(PGM4) 210819
0005.00 CALL PGM(PGM5) 210819
0006.00 ENDPGM 210819
***** End of data *****

- F3=Exit F5=Refresh F9=Retrieve F10=Cursor F11=Toggle F12=Cancel
F16=Repeat find F24=More keys

_ **Display Command String**

```
HARMONIZER REFF(JOEB/HARMONIZER PGM1V1)
            CMPRF(JOEB/HARMONIZER PGM1V2 JOEB/HARMONIZER PGM1
                V1 ())
            OUTF(JOEB/HARMONIZER PGM1MERGE)
            COMPOSITE(RR M AD IP R1)
```

Press ENTER to continue.

F3=Exit F5=Refresh F12=Cancel F13=How to use this display F24=More keys

Work with Members Using PDM

CSTST72A

```
File . . . . . HARMONIZER
Library . . . . . JOEB                    Position to . . . . . _____
```

Type options, press Enter.

2=Edit 3=Copy 4=Delete 5=Display 6=Print 7=Rename
8=Display description 9=Save 13=Change text 14=Compile 15=Create module...

Opt	Member	Type	Text
5	PGM1MERGE	CLP	program 1 version 1
—	PGM1V1	CLP	program 1 version 1
—	PGM1V2	CLP	program 1 version 2

Bottom

Parameters or command

===> _____

F3=Exit F4=Prompt F5=Refresh F6=Create
F9=Retrieve F10=Command entry F23=More options F24=More keys

Command prompting ended when user pressed F3.

Columns . . . : 1 80

Browse

JOEB/HARMONIZER

SEU==> PGM1MERGE

```

FMT **  ...+... 1 ...+... 2 ...+... 3 ...+... 4 ...+... 5 ...+... 6 ...+... 7 ...+... 8
***** Beginning of data *****
0001.00          PGM                               210819
0002.00          /* THIS IS PROGRAM1 VERSION 2 */  210819
0002.01          /* THIS IS PROGRAM 1 VERSION 1 */ 210819
0003.00          CALL          PGM(PGM1)          210819
0004.00          CALL          PGM(PGM2)          210819
0004.01          CALL          PGM(PGM4)          210819
0005.00          CALL          PGM(PGM5)          210819
0005.01          ENDPGM                             210819
***** End of data *****

```

F3=Exit F5=Refresh F9=Retrieve F10=Cursor F11=Toggle F12=Cancel
 F16=Repeat find F24=More keys